



# ***Novatek HDAL Design Specification - hd\_audiocapture***

---

**Copyright © 2018 Novatek Microelectronics Corp. All Rights Reserved.**

With respect to the information represented in this document, Novatek makes no warranty, expressed or implied, including the warranties of merchantability, fitness for a particular purpose and non-infringement, and does not assume any legal liability or responsibility for the accuracy, completeness or usefulness of any such information.

# Table of Content

Novatek HDAL Design Specification - hd_audiocapture .....	1
1 Introduction .....	4
1.1 Basic Flow .....	4
1.2 Single Trigger Operation .....	5
2 Function and data structure definition .....	7
2.1 General function .....	7
2.1.1 hd_audiocap_init .....	7
2.1.2 hd_audiocap_open .....	7
2.1.3 hd_audiocap_get .....	8
2.1.4 hd_audiocap_set .....	8
2.1.5 hd_audiocap_bind .....	9
2.1.6 hd_audiocap_start .....	10
2.1.7 hd_audiocap_stop .....	10
2.1.8 hd_audiocap_unbind .....	11
2.1.9 hd_audiocap_close .....	11
2.1.10 hd_audiocap_uninit .....	12
2.1.11 hd_audiocap_start_list .....	12
2.1.12 hd_audiocap_stop_list .....	13
2.1.13 hd_audiocap_pull_out_buf .....	13
2.1.14 hd_audiocap_release_out_buf .....	14
2.2 Data structure definition .....	15
2.2.1 HD_AUDIOCAP_SYSCAPS .....	16
2.2.2 HD_AUDIOCAP_DEV_CONFIG .....	17
2.2.3 HD_AUDIOCAP_SYSINFO .....	19
2.2.4 HD_AUDIOCAP_DRV_CONFIG .....	19
2.2.5 HD_AUDIOCAP_SSP_CONFIG .....	20
2.2.6 HD_AUDIOCAP_IN .....	20
2.2.7 HD_AUDIOCAP_OUT .....	21
2.2.8 HD_AUDIOCAP_VOLUME .....	21
2.2.9 HD_AUDIOCAP_POOL .....	22
2.2.10 HD_AUDIOCAP_AEC .....	22
2.2.11 HD_AUDIOCAP_ANR .....	23
2.2.12 HD_AUDIOCAP_PARAM_CLEAR_BUF .....	24
3 Debug command .....	25
3.1 proc command for IPC .....	25
3.1.1 Dump info .....	25
3.1.2 debug command .....	29
3.1.3 trace command .....	30
3.1.4 probe command .....	30
3.1.5 perf command .....	31
3.1.6 save command .....	31
3.2 Debug menu for IPC .....	32
3.3 proc command for NVR .....	32
3.3.1 Dump info .....	32




3.4	Debug menu for NVR .....	33
4	Sample Codes .....	33
4.1	audio_capture_only (IPC) .....	33
4.2	audio_livesound(NVR) .....	34
5	Frequently asked questions .....	38
5.1	[NVR ONLY] .....	38
5.2	[IPCAM ONLY] .....	38
5.2.1	Sample rate .....	38
5.2.2	Volume .....	38

# 1 Introduction

The major purpose of hd\_audiocapture is to get raw data from audio engine. This document will talk about the red block in the following diagram. The device driver is not the main point in this document.

## Sensor in



## Mic in



## Bitstream in




Front End

Back End

## 1.1 Basic Flow


The call sequence is needed to be done correctly for the unit. The standard starting flows of most modules are init, open, get, set, bind and start. The standard closing flows of most modules are stop, unbind, close and uninit. The basic flow is shown as below.



Now, below section in this chapter is mainly about what things to do in those functions above.

## 1.2 Single Trigger Operation

Single trigger operation is used to trigger the unit to do one job, such as to grab one PCM frame from audio capture. There are two types of functions for output port. The sequence for output port is pull and release. The flow is shown as below.

**Output**

## 2 Function and data structure definition

### 2.1 General function

#### 2.1.1 hd\_audiocap\_init

[Description]

Initialize the unit

[Syntax]

HD\_RESULT hd\_audiocap\_init(VOID);

[Parameter]

Value	Description
VOID	Not available

[Return Value]

Value	Description
HD_OK	Success
HD_ERR_NG	Failure

#### 2.1.2 hd\_audiocap\_open

[Description]

Open the unit

[Syntax]

HD\_RESULT hd\_audiocap\_open(HD\_IN\_ID in\_id, HD\_OUT\_ID out\_id, HD\_PATH\_ID\* p\_path\_id)

[Parameter]

Value	Description
-------	-------------

Copyright © 2018 Novatek Microelectronics Corp. All Rights Reserved.

With respect to the information represented in this document, Novatek makes no warranty, expressed or implied, including the warranties of merchantability, fitness for a particular purpose and non-infringement, and does not assume any legal liability or responsibility for the accuracy, completeness or usefulness of any such information.

in_id	id of input port.
out_id	id of output port.
p_path_id	pointer of the path id

**[Return Value]**

Value	Description
HD_OK	Success
HD_ERR_NG	Failure

### 2.1.3 hd\_audiocap\_get

**[Description]**

Get parameters from unit by path id

**[Syntax]**

HD\_RESULT hd\_audiocap\_get(HD\_PATH\_ID path\_id, HD\_AUDIOCAP\_PARAM\_ID id, VOID\* p\_param)

**[Parameter]**

Value	Description
path_id	the path id
id	id of parameters
p_param	pointer of parameters

**[Return Value]**

Value	Description
HD_OK	Success
HD_ERR_NG	Failure
HD_ERR_NOT_SUPPORT	Not support this parameter

### 2.1.4 hd\_audiocap\_set

**[Description]**

Set parameters to unit by path id



## [Syntax]

```
HD_RESULT hd_audiocap_set(HD_PATH_ID path_id, HD_AUDIOCAP_PARAM_ID id,  
VOID* p_param)
```

## [Parameter]

Value	Description
path_id	the path id
id	id of parameters
p_param	pointer of parameters

## [Return Value]

Value	Description
HD_OK	Success
HD_ERR_NG	Failure
HD_ERR_NOT_SUPPORT	Not support this parameter

## 2.1.5 hd\_audiocap\_bind

## [Description]

Bind this unit with destination unit

## [Syntax]

```
HD_RESULT hd_audiocap_bind(HD_OUT_ID out_id, HD_IN_ID dest_in_id)
```

## [Parameter]

Value	Description
out_id	id of output port.
dest_in_id	id of input port.

## [Return Value]

Value	Description
HD_OK	Success
HD_ERR_NG	Failure

## 2.1.6 hd\_audiocap\_start

### [Description]

Start the unit

### [Syntax]

HD\_RESULT hd\_audiocap\_start(HD\_PATH\_ID path\_id)

### [Parameter]

Value	Description
path_id	pointer of the path id

### [Return Value]

Value	Description
HD_OK	Success
HD_ERR_NG	Failure

## 2.1.7 hd\_audiocap\_stop

### [Description]

Stop the unit

### [Syntax]

HD\_RESULT hd\_audiocap\_stop(HD\_PATH\_ID path\_id)

### [Parameter]

Value	Description
path_id	pointer of the path id

### [Return Value]

Value	Description
HD_OK	Success
HD_ERR_NG	Failure

## 2.1.8 hd\_audiocap\_unbind

### [Description]

Unbind the unit

### [Syntax]

HD\_RESULT hd\_audiocap\_open(HD\_IN\_ID in\_id, HD\_OUT\_ID out\_id, HD\_PATH\_ID\* p\_path\_id)

### [Parameter]

Value	Description
in_id	id of input port.
out_id	id of output port.
p_path_id	pointer of the path id

### [Return Value]

Value	Description
HD_OK	Success
HD_ERR_NG	Failure

## 2.1.9 hd\_audiocap\_close

### [Description]

Close the unit

### [Syntax]

HD\_RESULT hd\_audiocap\_close(HD\_PATH\_ID path\_id)

### [Parameter]

Value	Description
path_id	pointer of the path id

### [Return Value]

Value	Description
HD_OK	Success
HD_ERR_NG	Failure

## 2.1.10 hd\_audiocap\_uninit

### [Description]

Uninitialize the unit

### [Syntax]

```
HD_RESULT hd_audiocap_uninit(VOID);
```

### [Parameter]

Value	Description
VOID	Not available

### [Return Value]

Value	Description
HD_OK	Success
HD_ERR_NG	Failure

## 2.1.11 hd\_audiocap\_start\_list

### [Description]

Do start for a list of paths

### [Syntax]

```
HD_RESULT hd_audiocap_start_list(HD_PATH_ID *path_id, UINT num);
```

### [Parameter]

Value	Description
path_id	An array of paths
num	The number of paths

### [Return Value]

Value	Description
HD_OK	Success
HD_ERR_NG	Failure

[Difference]

Chip	Description
IPC	All functions are NOT supported.
NVR	All functions are supported.

## 2.1.12 hd\_audiocap\_stop\_list

[Description]

Do stop for a list of paths

[Syntax]

```
HD_RESULT hd_audiocap_stop_list(HD_PATH_ID *path_id, UINT num);
```

[Parameter]

Value	Description
path_id	An array of paths
num	The number of paths

[Return Value]

Value	Description
HD_OK	Success
HD_ERR_NG	Failure

[Difference]

Chip	Description
IPC	All functions are NOT supported.
NVR	All functions are supported.

## 2.1.13 hd\_audiocap\_pull\_out\_buf

[Description]

Pull the audio frame buffer from unit

[Syntax]

```
HD_RESULT hd_audiocap_pull_out_buf(HD_PATH_ID path_id, HD_AUDIO_FRAME
```

\*p\_audio\_frame, INT32 wait\_ms)

[Parameter]

Value	Description
path_id	the path id
p_audio_frame	pointer of the output audio frame
wait_ms	timeout value in ms

[Return Value]

Value	Description
HD_OK	Success
HD_ERR_NG	Failure

[Difference]

Chip	Description
IPC	All functions are supported.
NVR	All functions are NOT supported.

## 2.1.14 hd\_audiocap\_release\_out\_buf

[Description]

Release the audio frame buffer which is get from unit

[Syntax]

HD\_RESULT hd\_audiocap\_release\_out\_buf(HD\_PATH\_ID path\_id, HD\_AUDIO\_FRAME \*p\_audio\_frame)

[Parameter]

Value	Description
path_id	the path id
p_audio_frame	pointer of the output audio p_audio_frame

[Return Value]

Value	Description
HD_OK	Success
HD_ERR_NG	Failure

Copyright © 2018 Novatek Microelectronics Corp. All Rights Reserved.

With respect to the information represented in this document, Novatek makes no warranty, expressed or implied, including the warranties of merchantability, fitness for a particular purpose and non-infringement, and does not assume any legal liability or responsibility for the accuracy, completeness or usefulness of any such information.

[Difference]

Chip	Description
IPC	All functions are supported.
NVR	All functions are NOT supported.

## 2.2 Data structure definition

The function `hd_audiocap_get` and `hd_audiocap_set` provides the following parameter IDs:

- `HD_AUDIOCAP_PARAM_DEVCOUNT`
  - ☐ NVR/IPC. support get with ctrl path
  - ☐ using `HD_DEVCOUNT` struct (device id max count)
- `HD_AUDIOCAP_PARAM_SYSCAPS`
  - ☐ NVR/IPC. support get with ctrl path
  - ☐ using `HD_AUDIOCAP_SYSCAPS`
- `HD_AUDIOCAP_PARAM_SYSINFO`
  - ☐ NVR/IPC. support get with ctrl path
  - ☐ using `HD_AUDIOCAP_SYSINFO`
- `HD_AUDIOCAP_PARAM_DEV_CONFIG`
  - ☐ NVR/IPC. support get/set with ctrl path
  - ☐ using `HD_AUDIOCAP_DEV_CONFIG` struct
- `HD_AUDIOCAP_PARAM_DRV_CONFIG`
  - ☐ NVR/IPC. support get/set with ctrl path
  - ☐ using `HD_AUDIOCAP_DRV_CONFIG` struct
- `HD_AUDIOCAP_PARAM_IN`
  - ☐ NVR/IPC. support get/set with i/o path
  - ☐ using `HD_AUDIOCAP_IN` struct
- `HD_AUDIOCAP_PARAM_OUT`
  - ☐ NVR/IPC. support get/set with i/o path
  - ☐ using `HD_AUDIOCAP_OUT` struct
- `HD_AUDIOCAP_PARAM_OUT_AEC`

- ☐ IPC only. support get/set with i/o path
- ☐ using HD\_AUDIOCAP\_AEC struct
- HD\_AUDIOCAP\_PARAM\_OUT\_ANR
  - ☐ IPC only. support get/set with i/o path
  - ☐ using HD\_AUDIOCAP\_ANR struct
- HD\_AUDIOCAP\_PARAM\_VOLUME
  - ☐ NVR/IPC. support get/set with ctrl path
  - ☐ using HD\_AUDIOCAP\_VOLUME struct
- HD\_AUDIOCAP\_PARAM\_BUFINFO
  - ☐ IPC only. support get with ctrl path
  - ☐ using HD\_AUDIOCAP\_BUFINFO struct

## 2.2.1 HD\_AUDIOCAP\_SYSCAPS

[Description]

System capability

[Parameter]

Value	Description
dev_id	device id
chip_id	chip id of this device
max_in_count	max count of input of this device
max_out_count	max count of output of this device
dev_caps	capability of device, combine caps of HD_DEVICE_CAPS and HD_AUDIOCAP_DEVCAPS
in_caps	capability of input, cap of HD_AUDIO_CAPS
out_caps	capability of output, cap of HD_AUDIO_CAPS
support_in_sr	sample rate capability of input, cap of HD_AUDIOCAP_SRCAPS
support_out_sr	sample rate capability of output, cap of HD_AUDIOCAP_SRCAPS



## 2.2.2 HD\_AUDIOCAP\_DEV\_CONFIG

[Description]

Device configuration.

IPC: support close-time change.

[Parameter]

Value	Description
in_max.sample_rate	NVR/IPC. maximum input sample rate Please refer to HD_AUDIO_SR enum. Default value: HD_AUDIO_SR_48000 IPC: support close-time change.
in_max.sample_bit	NVR/IPC. maximum input sample bit Please refer to HD_AUDIO_BIT_WIDTH enum. Default value: HD_AUDIO_BIT_WIDTH_16 IPC: support close-time change.
in_max.mode	NVR/IPC. maximum input sound mode Please refer to HD_AUDIO_SOUND_MODE enum. Default value: HD_AUDIO_SOUND_MODE_STEREO IPC: support close-time change.
in_max.frame_sample	NVR/IPC. maximum sample count of each frame Value range: 1024, 2048, 3072, 4096 Default value: 1024 IPC: support close-time change.
frame_num_max	NVR/IPC. maximum frame number in buffer Value range: [4, 50] Default value: 10 IPC: support close-time change.
out_max.sample_rate	NVR/IPC. maximum output sample rate. Please refer to HD_AUDIO_SR enum Value is 0: not support resampling Default value: 0 IPC: support close-time change.
aec_max.enabled	NVR/IPC. AEC enable

Copyright © 2018 Novatek Microelectronics Corp. All Rights Reserved.

With respect to the information represented in this document, Novatek makes no warranty, expressed or implied, including the warranties of merchantability, fitness for a particular purpose and non-infringement, and does not assume any legal liability or responsibility for the accuracy, completeness or usefulness of any such information.

	Value is 0: not support AEC Value is 1: support AEC Default value: 0 IPC: support close-time change.
aec_max.leak_estimate_enabled	NVR/IPC. AEC leak estimate enable Value is 0: disable aec leak estimate Value is 1: enable aec leak estimate Default value: 0 IPC: support close-time change.
aec_max.leak_estimate_value	NVR/IPC. AEC initial condition of the leak estimate Value range: [25, 99] Default value: 0 IPC: support close-time change.
aec_max.noise_cancel_level	NVR/IPC. AEC noise cancel level Value range: [-40, -3] Default value: 0 IPC: support close-time change.
aec_max.echo_cancel_level	NVR/IPC. AEC echo cancel level Value range: [-60, -30] Default value: 0 IPC: support close-time change.
aec_max.filter_length	NVR/IPC. AEC internal filter length Default value: 0 IPC: support close-time change.
aec_max.frame_size	NVR/IPC. AEC internal frame size Default value: 0 IPC: support close-time change.
aec_max.notch_radius	NVR/IPC. AEC notch filter radius. Value range: [0, 1000] Default value: 0 IPC: support close-time change.
aec_max.lb_channel	NVR/IPC. AEC audio output loopback channel. Please refer to HD_AUDIOCAP_LB_CH. Default value: 0 IPC: support stop-time change.

anr_max.enabled	NVR/IPC. ANR enable Value is 0: not support ANR Value is 1: support ANR Default value: 0 IPC: support close-time change.
anr_max.suppress_level	NVR/IPC. ANR suppression level of noise Value range: [3, 35] Default value: 0 IPC: support close-time change.
anr_max.hpf_cut_off_freq	NVR/IPC. ANR cut-off frequency of HPF pre-filtering Default value: 0 IPC: support close-time change.
anr_max.bias_sensitive	NVR/IPC. ANR bias sensitive Value range: [1, 9] Default value: 0 IPC: support close-time change.
data_pool	NVR only. pool memory information

### 2.2.3 HD\_AUDIOCAP\_SYSINFO

[Description]

System information

[Parameter]

Value	Description
dev_id	device id
cur_in_sample_rate	current input sample rate
cur_sample_bit	current sample bit width
cur_mode	current sound mode
cur_out_sample_rate	current output sample rate

### 2.2.4 HD\_AUDIOCAP\_DRV\_CONFIG

[Description]

Copyright © 2018 Novatek Microelectronics Corp. All Rights Reserved.

With respect to the information represented in this document, Novatek makes no warranty, expressed or implied, including the warranties of merchantability, fitness for a particular purpose and non-infringement, and does not assume any legal liability or responsibility for the accuracy, completeness or usefulness of any such information.

## Driver configuration

### [Parameter]

Value	Description
mono	IPC only. audio mono channel Please refer to HD_AUDIO_MONO enum. Default value: HD_AUDIO_MONO_RIGHT IPC: support stop-time change.
ssp_config	NVR only. audio ssp config

## 2.2.5 HD\_AUDIOCAP\_SSP\_CONFIG

### [Description]

SSP configuration

### [Parameter]

Value	Description
ssp_num	NVR only. the hw path for this ssp
enable	NVR only. enable for each ssp interface
ssp_chan	NVR only. the channel count for this ssp
sample_size	NVR only. audio sample size
sample_rate	NVR only. audio sample rate
ssp_clock	NVR only. ssp clock for each ssp interface
bit_clock	NVR only. bit clock for each ssp interface
ssp_master	NVR only. select mode for this ssp
live_sound_ch	NVR only. channel source of live sound

## 2.2.6 HD\_AUDIOCAP\_IN

### [Description]

Input parameter

### [Parameter]

Value	Description
sample_rate	sample rate

	Please refer to HD_AUDIO_SR enum. Default value: HD_AUDIO_SR_48000 IPC: support stop-time change.
sample_bit	sample bit Please refer to HD_AUDIO_BIT_WIDTH enum. Default value: HD_AUDIO_BIT_WIDTH_16 IPC: support stop-time change.
mode	sound mode Please refer to HD_AUDIO_SOUND_MODE enum. Default value: HD_AUDIO_SOUND_MODE_STEREO IPC: support stop-time change.
frame_sample	sample count of each frame Value range: Default value: 1024 IPC: support stop-time change.

## 2.2.7 HD\_AUDIOCAP\_OUT

[Description]

Output parameter

[Parameter]

Value	Description
sample_rate	output sample rate (for resampling) Please refer to HD_AUDIO_SR enum. Value is 0: disable resampling Default value: 0 IPC: support stop-time change.

## 2.2.8 HD\_AUDIOCAP\_VOLUME

[Description]

**Copyright © 2018 Novatek Microelectronics Corp. All Rights Reserved.**

With respect to the information represented in this document, Novatek makes no warranty, expressed or implied, including the warranties of merchantability, fitness for a particular purpose and non-infringement, and does not assume any legal liability or responsibility for the accuracy, completeness or usefulness of any such information.

Input volume.

[Parameter]

Value	Description
volume	input volume Value range: [0,100] Default value: 100.

## 2.2.9 HD\_AUDIOCAP\_POOL

[Description]

Pool memory information

[Parameter]

Value	Description
ddr_id	DDR ID
frame_sample_size	the buffer size of audio frame
counts	count of buffer
max_counts	max counts of buffer
min_counts	min counts of buffer
mode	pool mode

## 2.2.10 HD\_AUDIOCAP\_AEC

[Description]

AEC configuration

[Parameter]

Value	Description
enabled	AEC enable Value is 0: disable AEC Value is 1: enable AEC Default value: 0 IPC: support stop-time change.
leak_estimate_enabled	leak estimate enable

	Value is 0: disable aec leak estimate Value is 1: enable aec leak estimate Default value: 0 IPC: support stop-time change.
leak_estimate_value	initial condition of the leak estimate Value range: [25, 99] Default value: 0 IPC: support stop-time change.
noise_cancel_level	noise cancel level Value range: [-40, -3] Default value: 0 IPC: support stop-time change.
echo_cancel_level	echo cancel level Value range: [-60, -30] Default value: 0 IPC: support stop-time change.
filter_length	internal filter length Default value: 0 IPC: support stop-time change.
frame_size	internal frame size Default value: 0 IPC: support stop-time change.
notch_radius	notch filter radius Value range: [0, 1000] Default value: 0 IPC: support stop-time change.
lb_channel	audio output loopback channel Please refer to HD_AUDIOCAP_LB_CH. Default value: 0 IPC: support stop-time change.

## 2.2.11 HD\_AUDIOCAP\_ANR

[Description]

ANR configuration

[Parameter]

Value	Description
enabled	ANR enable Value is 0: disable ANR Value is 1: enable ANR Default value: 0 IPC: support stop-time change.
suppress_level	suppression level of noise Value range: [3, 35] Default value: 0 IPC: support stop-time change.
hpf_cut_off_freq	cut-off frequency of HPF pre-filtering Default value: 0 IPC: support stop-time change.
bias_sensitive	bias sensitive Value range: [1, 9] Default value: 0 IPC: support stop-time change.

## 2.2.12 HD\_AUDIOCAP\_PARAM\_CLEAR\_BUF

[Description]

Clear audio data in the queue.

[Parameter]

No parameters.



## 3 Debug command

The audiocapture module supports two kinds of debug mechanism for user. User can use proc command or debug menu to debug.

### 3.1 proc command for IPC

#### 3.1.1 Dump info

```
[dump info]
cat /proc/hdal/acap/info
```

The result will show the audiocapture information by five parts.

1. **PATH & BIND**: bind status of hd\_audiocapture.
2. **DEV CONFIG**: device configuration, referring to HD\_AUDIOCAP\_DEV\_CONFIG.
3. **DRV CONFIG**: driver configuration, referring to HD\_AUDIOCAP\_DRV\_CONFIG.
4. **Volume**: volume configuration, referring to HD\_AUDIOCAP\_VOLUME.
5. **IN FRAME**: input configuration, referring to HD\_AUDIOCAP\_IN.
6. **OUT FRAME**: output configuration for resampling, referring to HD\_AUDIOCAP\_OUT.
7. **AEC**: AEC configuration, referring to HD\_AUDIOCAP\_AEC.
8. **ANR**: ANR configuration, referring to HD\_AUDIOCAP\_ANR.

#### [PATH & BIND]

Status	Description
in	input id of path
out	output id of path
state	state of path
bind_src	current binding source of input
bind_dest	current binding source of output

#### [DEV CONFIG]

Status	Description
max	device ID

in.sr	maximum sample rate
in.ch	maximum channel count (sound mode)
in.bit	maximum bit width
in.frm_sample	maximum frame sample
frm_num	maximum frame number
aec.en	AEC enable
aec.leak_est_en	AEC leak estimate enable
aec.leak_est	AEC initial condition of the leak estimate
aec.noise_lvl	AEC noise cancel level
aec.echo_lvl	AEC echo cancel level
aec.filter_len	AEC internal filter length
aec.frm_size	AEC internal frame size
aec.notch_radius	AEC notch filter radius
aec.lb_ch	AEC audio output loopback channel
anr.en	ANR enable
anr.suppress_level	ANR maximum suppression level of noise
anr.hpf_freq	ANR cut-off frequency of HPF pre-filtering
anr.bias_sensitive	ANR bias sensitive

#### [DRV CONFIG]

Status	Description
mono	audio mono channel

#### [VOLUME]

Status	Description
vol	input volume

#### [IN FRAME]

Value	Description
in	input id of path
sr	current input sample rate
ch	current input channel count (sound mode)
bit	current input bit width
frm_sample	current frame sample

### [OUT FRAME]

Value	Description
out	output id of path
sr	current output sample rate (for resampling)

### [AEC CONFIG]

Status	Description
out	output id of path
aec.en	AEC enable
aec.leak_est_en	AEC leak estimate enable
aec.leak_est	AEC initial condition of the leak estimate
aec.noise_lvl	AEC noise cancel level
aec.echo_lvl	AEC echo cancel level
aec.filter_len	AEC internal filter length
aec.frm_size	AEC internal frame size
aec.notch_radius	AEC notch filter radius
aec.lb_ch	AEC audio output loopback channel

### [ANR CONFIG]

Status	Description
out	output id of path
anr.en	ANR enable
anr.suppress_level	ANR maximum suppression level of noise
anr.hpf_freq	ANR cut-off frequency of HPF pre-filtering
anr.bias_sensitive	ANR bias sensitive

### Example:

----- AUDIOCAP 0 PATH & BIND -----				
in	out	state	bind_src	bind_dest
0	0	START (null)		AUDIOOUT_0_IN_0
----- AUDIOCAP 0 DEV CONFIG -----				
max				
0				
in.sr	in.ch	in.bit	in.frm_sample	frm_num
48000	2	16	1024	10

CONFIDENTIAL

aec.en	aec.leak_est_en	aec.leak_est	aec.noise_lvl									
0	0	0	0									
aec.echo_lvl	aec.filter_len	aec.frm_size	aec.notch_radius	aec.lb_ch								
0	0	0	0	0								
anr.en	anr.suppress_level	anr.hpf_freq	anr.bias_sensitive									
0	0	0	0									
----- AUDIOCAP 0 DRV CONFIG -----												
mono												
1												
----- AUDIOCAP 0 VOLUME -----												
vol												
100												
----- AUDIOCAP 0 IN FRAME -----												
in	sr	ch	bit	frm_sample								
0	48000	2	16	1024								
----- AUDIOCAP 0 OUT FRAME -----												
out	sr											
0	0											
----- AUDIOCAP 0 AEC CONFIG -----												
out												
0												
aec.en	aec.leak_est_en	aec.leak_est	aec.noise_lvl									
0	0	0	0									
aec.echo_lvl	aec.filter_len	aec.frm_size	aec.notch_radius	aec.lb_ch								
0	0	0	0	0								
----- AUDIOCAP 0 ANR CONFIG -----												
out	anr.en	anr.suppress_level	anr.hpf_freq	anr.bias_sensitive								
0	0	0	0	0								
----- AUDIOCAP 0 OUT WORK STATUS -----												
out	NEW	drop	wrn	err	PROC	drop	wrn	err	PUSH	drop	wrn	err
0	47	0	0	0	47	0	0	0	47	0	0	0
----- AUDIOCAP 0 USER WORK STATUS -----												

out	PULL	drop	wrn	err	REL
0	0	0	0	0	0

### 3.1.2 debug command

```
[debug port]
echo debug [dev] [i/o] [mask] > /proc/hdal/acap/cmd
where [dev] = d0 , [i/o] = i0, i1, i2, ..., o0, o1, o2, ... , [mask] = show info mask

[ Sample ]
echo debug d0 o0 mfff > /proc/hdal/acap/cmd
```

this debug command can show more debug log on console

```
root@NVTEVM:~$ hd_audio_capture_only
[ 2243.828960] hd_reset - begin
[ 2243.833958] hd_reset - end
HDAL_VERSION: 00[ 2243.838071] "audcap".out[0]: set aud-max-frame(10) aud-max-bitpersec(16)
aud-max-sndmode(2) aud-max-samplerate(48000,-2141852768)
[ 2243.851277] "audcap".ctrl: set param(00019016)=1024

[ 2243.858471] "audcap".out[0]: set param(00019005)=10
[ 2243.864460] "audcap".out[0]: set param(00019018)=0
[ 2243.870302] "audcap".out[0]: set param(00019011)=0
[ 2243.876057] "audcap".out[0]: set param(00019012)=0
[ 2243.881829] "audcap".out[0]: set aud-max-frame(10) aud-max-bitpersec(16) aud-max-sndmode(2)
aud-max-samplerate(0,164)
[ 2243.893387] "audcap".out[0]: set param(00019003)=1
[ 2243.899139]
[ 2243.899139] "audcap".out[0]: open begin, state=0
[ 2243.906272] "audcap".out[0]: cmd OPEN
[ 2243.911160] "audcap".out[0]: open end, state=1
[ 2243.916587] "audcap".ctrl: get param(00019014)=310398976
[ 2243.922857] "audcap".ctrl: get param(00019015)=45928
[ 2243.928779] "audcap".out[0]: set aud-bitpersec(16) aud-sndmode(2) samplecnt(0)
[ 2243.936955] "audcap".out[0]: set aud-samplerate(48000,2)
[ 2243.943222] "audcap".ctrl: set param(00019010)=1024
```

```
[ 2243.949063] "audcap".out[0]: set aud-samplerate(0,1024)
[ 2243.955380]
[ 2243.955380] "audcap".out[0]: start begin, state=1
[ 2243.962607] "audcap".out[0]: cmd RDYSYNC
[ 2243.967486] "audcap".out[0]: cmd START
[ 2244.173095] "audcap".out[0]: start end, state=2
Enter q to exit, Enter d to debug
```

```
dump main bitstream to file (/mnt/sd/audio_bs_16_2_48000_pcm.dat) ....
```

```
if you want to stop, enter "q" to exit !!
```

```
q
[ 2247.181497]
[ 2247.181497] "audcap".out[0]: stop begin, state=2
[ 2247.188685] "audcap".out[0]: cmd STOP
[ 2247.193495] "audcap".out[0]: stop end, state=1
[ 2247.198928]
[ 2247.198928] "audcap".out[0]: close begin, state=1
[ 2247.206151] "audcap".out[0]: cmd CLOSE
[ 2247.210976] "audcap".out[0]: close end, state=0
```

### 3.1.3 trace command

```
[trace port]
echo trace [dev] [i/o] [mask] > /proc/hdal/acap/cmd
where [dev] = d0 , [i/o] = i0, i1, i2, ..., o0, o1, o2, ... , [mask] = show info mask

[ sample ]
echo trace d0 o0 mfff > /proc/hdal/acap/cmd
```

this trace command could enable module internal debug message to know what's going on for the AUDIOCAPTURE module.

### 3.1.4 probe command

```
[probe port]
```

Copyright © 2018 Novatek Microelectronics Corp. All Rights Reserved.

With respect to the information represented in this document, Novatek makes no warranty, expressed or implied, including the warranties of merchantability, fitness for a particular purpose and non-infringement, and does not assume any legal liability or responsibility for the accuracy, completeness or usefulness of any such information.

```
echo probe [dev] [i/o] [mask] > /proc/hdal/acap/cmd
where [dev] = d0 , [i/o] = i0, i1, i2, ..., o0, o1, o2, ... , [mask] = show info mask

[ Sample ]

echo probe d0 o0 mffff > /proc/hdal/acap/cmd
```

this probe command could print per-data status

```
[ 2522.848423] "audcap".out[0] - NEW - new -- h=00000001 size=00000000 addr=00000001 OK
[ 2522.857270] "audcap".out[0] - PUSH - rel -- h=00000009 (result=0) OK
[ 2522.864702] "audcap".out[0] - PUSH - rel -- h=00000001 (result=0) OK
[ 2522.868444] "audcap".out[0] - NEW - new -- h=00000002 size=00000000 addr=00000002 OK
[ 2522.880814] "audcap".out[0] - PUSH - rel -- h=00000002 (result=0) OK
[ 2522.889769] "audcap".out[0] - NEW - new -- h=00000001 size=00000000 addr=00000001 OK
[ 2522.898557] "audcap".out[0] - PUSH - rel -- h=00000001 (result=0) OK
[ 2522.911102] "audcap".out[0] - NEW - new -- h=00000001 size=00000000 addr=00000001 OK
[ 2522.919878] "audcap".out[0] - PUSH - rel -- h=00000001 (result=0) OK
```

### 3.1.5 perf command

```
[perf port]

echo perf [dev] [i/o] > /proc/hdal/acap/cmd

[ Sample ]

echo perf d0 o0 > /proc/hdal/acap/cmd
```

this perf command could print data count per second

```
[ 86.934367] "audcap".out[0] Perf! -- (Audio) 0 KSample/sec
[ 87.935854] "audcap".out[0] Perf! -- (Audio) 0 KSample/sec
[ 88.938517] "audcap".out[0] Perf! -- (Audio) 0 KSample/sec
```

### 3.1.6 save command

```
[save port]

echo save [dev] [i/o] [count] > /proc/hdal/acap/cmd
where [count] means how many i/o datas to save

[ Sample ]
```

```
echo save d0 o0 > /proc/hdal/acap /cmd
```

this save command could save i/o data to SDCard for debug purpose.

```
[ 2623.112009] save i/o begin: "audcap".out[0] count=1
[ 2623.131650] "audcap".out[0] Save -- h=00000001 t=000000009dbbc1ac (ARAW: 16.2.48000 9400c368
00000000 4096)
[ 2623.142721] "audcap".out[0] Save -- //mnt//sd//isf_ audcap_out[0]_16_2_48000_c0.aud ok
[ 2623.151593] save port end
```

## 3.2 Debug menu for IPC

The currently supported audiocapture module debug menu is as below.

```
=====
AUDIOCAP
-----
```

```
01 : dump info
-----
```

User can choose the number to dump the status what you want. The dump result is just like the example shows on 3.1.1.

The proc command and debug menu mapping table is as below:

Proc command	Debug menu
cat /proc/hdal/acap/info	dump audiocapture information

## 3.3 proc command for NVR

### 3.3.1 Dump info

```
[dump info]
cat /proc/videograph/hdal_setting
```

The result will show the audiocapture information.

```
root@NVTEVM:/$ cat /proc/videograph/hdal_setting
```

Copyright © 2018 Novatek Microelectronics Corp. All Rights Reserved.

With respect to the information represented in this document, Novatek makes no warranty, expressed or implied, including the warranties of merchantability, fitness for a particular purpose and non-infringement, and does not assume any legal liability or responsibility for the accuracy, completeness or usefulness of any such information.



----- AUDIOCAP 0 PATH & BIND -----				
in	out	state	bind_src	bind_dest
0	0	START	-	AUDIOENC_0_IN_0
----- AUDIOCAP 0 IN -----				
out	rate	bit	samples	
0	8000	16	320 MONO	

## 3.4 Debug menu for NVR

Calling hd\_debug\_run\_menu() from app will pop out debug\_menu.

The currently supported audiocapture module debug menu is as below.

=====				
AUDIOCAP				
-----				
01 : dump status				
-----				
254 : Quit				
255 : Return				
-----				
1				
Run: 01 : dump status				
----- AUDIOCAP 0 PATH & BIND -----				
in	out	state	bind_src	bind_dest
0	0	START	-	AUDIOENC_0_IN_0
----- AUDIOCAP 0 IN -----				
out	rate	bit	samples	
0	8000	16	320 MONO	

User can choose the number to dump the status what you want. The dump result is just like the example shown on 3.3.

## 4 Sample Codes

### 4.1 audio\_capture\_only (IPC)

This sample code demonstrates how to use the single trigger operation to get the PCM data.

```
/* set cap configuration */
ret = hd_audiocap_open(0, HD_AUDIOCAP_0_CTRL, &audio_cap_ctrl); //open this for device control
audio_dev_cfg.in_max.sample_rate = HD_AUDIO_SR_48000;
audio_dev_cfg.in_max.sample_bit = HD_AUDIO_BIT_WIDTH_16;
```

Copyright © 2018 Novatek Microelectronics Corp. All Rights Reserved.

With respect to the information represented in this document, Novatek makes no warranty, expressed or implied, including the warranties of merchantability, fitness for a particular purpose and non-infringement, and does not assume any legal liability or responsibility for the accuracy, completeness or usefulness of any such information.

```

audio_dev_cfg.in_max.mode = HD_AUDIO_SOUND_MODE_STEREO;
audio_dev_cfg.in_max.frame_sample = 1024;
audio_dev_cfg.frame_num_max = 10;
ret = hd_audiocap_set(audio_cap_ctrl, HD_AUDIOCAP_PARAM_DEV_CONFIG, &audio_dev_cfg);
if (ret != HD_OK) { return ret; }
audio_drv_cfg.mono = HD_AUDIO_MONO_RIGHT;
ret = hd_audiocap_set(audio_cap_ctrl, HD_AUDIOCAP_PARAM_DRV_CONFIG, &audio_drv_cfg);
if (ret != HD_OK) { return ret; }

/* Set cap parameter */
ret = hd_audiocap_open(HD_AUDIOCAP_0_IN_0, HD_AUDIOCAP_0_OUT_0, &audio_cap_path);
audio_cap_param.sample_rate = HD_AUDIO_SR_48000;
audio_cap_param.sample_bit = HD_AUDIO_BIT_WIDTH_16;
audio_cap_param.mode = HD_AUDIO_SOUND_MODE_STEREO;
audio_cap_param.frame_sample = 1024;
ret = hd_audiocap_set(audio_cap_path, HD_AUDIOCAP_PARAM_IN, &audio_cap_param);
if (ret != HD_OK) { return ret; }

/* Pull out buffer */
#define PHY2VIRT_MAIN(pa) (vir_addr_main + (pa - phy_buf_main.buf_info.phy_addr))

ret = hd_audiocap_pull_out_buf(audio_cap_path, &data_pull, 200);

if (ret == HD_OK) {
    UINT8 *ptr = 0;
    UINT32 size = 0;
    hd_audiocap_get(audio_cap_ctrl, HD_AUDIOCAP_PARAM_BUFINFO, &phy_buf_main);
    vir_addr_main = (UINT32)hd_common_mem_mmap(HD_COMMON_MEM_MEM_TYPE_CACHE,
                                                phy_buf_main.buf_info.phy_addr,
                                                phy_buf_main.buf_info.buf_size);

    ptr = (UINT8 *)PHY2VIRT_MAIN(data_pull.phy_addr[0]);
    size = data_pull.size;
}

/* Release out buffer */
ret = hd_audiocap_release_out_buf(audio_cap_path, &data_pull);
hd_common_mem_munmap((void *)vir_addr_main, phy_buf_main.buf_info.buf_size);

```

## 4.2 audio\_livesound(NVR)

audiocapture doesn't support push/pull operation. User must bind it with audioenc or audioout to get audio data or livesound functions. The following demonstrates how to run livesound by using binding method.

```

#include <stdio.h>
#include <unistd.h>
#include <stdlib.h>
#include <string.h>
#include <signal.h>
#include <pthread.h>

```

Copyright © 2018 Novatek Microelectronics Corp. All Rights Reserved.

With respect to the information represented in this document, Novatek makes no warranty, expressed or implied, including the warranties of merchantability, fitness for a particular purpose and non-infringement, and does not assume any legal liability or responsibility for the accuracy, completeness or usefulness of any such information.

```
#include "hdal.h"

typedef struct _AUDIO_LIVESOUND {
    UINT32 is_exit;
    HD_PATH_ID audcap_path_id;
    HD_PATH_ID audout_path_id;
} AUDIO_LIVESOUND;

HD_RESULT init_module(void)
{
    HD_RESULT ret;
    if((ret = hd_audiocap_init()) != HD_OK)
        return ret;
    if((ret = hd_audioout_init()) != HD_OK)
        return ret;
    return HD_OK;
}

HD_RESULT open_module(AUDIO_LIVESOUND *p_ls_info)
{
    HD_RESULT ret;
    if((ret = hd_audiocap_open(HD_AUDIOCAP_0_IN_0, HD_AUDIOCAP_0_OUT_0,
    &p_ls_info->audcap_path_id)) != HD_OK)
        return ret;
    if((ret = hd_audioout_open(HD_AUDIOOUT_0_IN_0, HD_AUDIOOUT_0_OUT_0,
    &p_ls_info->audout_path_id)) != HD_OK)
        return ret;
    return HD_OK;
}

HD_RESULT close_module(AUDIO_LIVESOUND *p_ls_info)
{
    HD_RESULT ret;
    if((ret = hd_audiocap_close(p_ls_info->audcap_path_id)) != HD_OK)
        return ret;
    if((ret = hd_audioout_close(p_ls_info->audout_path_id)) != HD_OK)
        return ret;
    return HD_OK;
}

HD_RESULT exit_module(void)
{
    HD_RESULT ret;
    if((ret = hd_audiocap_uninit()) != HD_OK)
        return ret;
    if((ret = hd_audioout_uninit()) != HD_OK)
        return ret;
    return HD_OK;
}

HD_RESULT set_param(AUDIO_LIVESOUND *p_livesound_info)
{
    HD_RESULT ret;
    HD_AUDIOCAP_IN audicap_param;
    HD_AUDIOOUT_OUT audioout_param;
```

Copyright © 2018 Novatek Microelectronics Corp. All Rights Reserved.

With respect to the information represented in this document, Novatek makes no warranty, expressed or implied, including the warranties of merchantability, fitness for a particular purpose and non-infringement, and does not assume any legal liability or responsibility for the accuracy, completeness or usefulness of any such information.

```

//set audiocap parameters
ret = hd_audiocap_get(p_livesound_info->audcap_path_id, HD_AUDIOCAP_PARAM_IN,
&audiocap_param);
if (ret != HD_OK) {
    printf("hd_audiocap_get(HD_AUDIOCAP_PARAM_IN) fail\n");
    goto exit;
}
audiocap_param.sample_rate = HD_AUDIO_SR_8000;
audiocap_param.sample_bit = HD_AUDIO_BIT_WIDTH_16;
audiocap_param.mode = HD_AUDIO_SOUND_MODE_MONO;
audiocap_param.frame_sample = 320; // for 25fps: 8000/25=320
ret = hd_audiocap_set(p_livesound_info->audcap_path_id, HD_AUDIOCAP_PARAM_IN,
&audiocap_param);
if (ret != HD_OK) {
    printf("hd_audiocap_set(HD_AUDIOCAP_PARAM_IN) fail\n");
    goto exit;
}

//set audioout parameters
ret = hd_audioout_get(p_livesound_info->audout_path_id, HD_AUDIOOUT_PARAM_OUT,
&audioout_param);
if (ret != HD_OK) {
    printf("hd_audioout_get(HD_AUDIOOUT_PARAM_OUT) fail\n");
    goto exit;
}
audioout_param.sample_rate = HD_AUDIO_SR_8000;
audioout_param.sample_bit = HD_AUDIO_BIT_WIDTH_16;
audioout_param.mode = HD_AUDIO_SOUND_MODE_MONO;
ret = hd_audioout_set(p_livesound_info->audout_path_id, HD_AUDIOOUT_PARAM_OUT,
&audioout_param);
if (ret != HD_OK) {
    printf("hd_audioout_set(HD_AUDIOOUT_PARAM_OUT) fail\n");
    goto exit;
}

exit:
    return ret;
}

int main(void)
{
    HD_RESULT ret;
    INT key;
    AUDIO_LIVESOUND livesound_info = {0};

    //init hda1
    ret = hd_common_init(1);
    if(ret != HD_OK) {
        printf("common init fail\n");
        goto exit;
    }

    // init audiocap and audioout modules
    ret = init_module();
    if(ret != HD_OK) {
        printf("init fail\n");
    }
}

```

Copyright © 2018 Novatek Microelectronics Corp. All Rights Reserved.

With respect to the information represented in this document, Novatek makes no warranty, expressed or implied, including the warranties of merchantability, fitness for a particular purpose and non-infringement, and does not assume any legal liability or responsibility for the accuracy, completeness or usefulness of any such information.

```

    goto exit;
}

//open audiocap and audioout modules
ret = open_module(&livesound_info);
if(ret != HD_OK) {
    printf("open fail\n");
    goto exit;
}

//setup runtime parameters
ret = set_param(&livesound_info);
if(ret != HD_OK) {
    printf("set param fail\n");
    goto exit;
}

//bind live sound: audiocap -> audioout
ret = hd_audiocap_bind(HD_AUDIOCAP_0_OUT_0, HD_AUDIOOUT_0_IN_0);
if(ret != HD_OK) {
    printf("bind fail\n");
    goto exit;
}

//start to run
ret = hd_audiocap_start(livesound_info.audcap_path_id);
if(ret != HD_OK) {
    printf("start audiocap fail\n");
    goto exit;
}
ret = hd_audioout_start(livesound_info.audout_path_id);
if(ret != HD_OK) {
    printf("start audioout fail\n");
    goto exit;
}

//main waiting loop
printf("Enter q to exit\n");
while (1) {
    key = getchar();
    if (key == 'q') {
        livesound_info.is_exit = 1;
        break;
    }
}

//stop modules and unbind the connection
ret = hd_audiocap_stop(livesound_info.audcap_path_id);
if(ret != HD_OK) {
    printf("stop audiocap fail\n");
}
ret = hd_audioout_stop(livesound_info.audout_path_id);
if(ret != HD_OK) {
    printf("stop audiocap fail\n");
}
ret = hd_audiocap_unbind(HD_AUDIOCAP_0_OUT_0);
if(ret != HD_OK) {

```

Copyright © 2018 Novatek Microelectronics Corp. All Rights Reserved.

With respect to the information represented in this document, Novatek makes no warranty, expressed or implied, including the warranties of merchantability, fitness for a particular purpose and non-infringement, and does not assume any legal liability or responsibility for the accuracy, completeness or usefulness of any such information.

```
        printf("unbind fail\n");
    }

exit:
    //close and uninit modules
    ret = close_module(&livesound_info);
    if(ret != HD_OK) {
        printf("close fail\n");
    }
    ret = exit_module();
    if(ret != HD_OK) {
        printf("exit fail\n");
    }
    ret = hd_common_uninit();
    if(ret != HD_OK) {
        printf("uninit fail\n");
    }
    return 0;
}
```

```
}}
```

## 5 Frequently asked questions

### 5.1 [NVR ONLY]

TBD

### 5.2 [IPCAM ONLY]

#### 5.2.1 Sample rate

The sample rate of audiocapture and audioout must be the same when they start simultaneously.

#### 5.2.2 Volume

Volume mapping table. When volume is larger than 100 (100~160), each step will increase the volume by 0.5 dB digital gain.

Volume	Step	dB
0	0	mute
1-11	1	-27
12-23	2	-24
24-35	3	-21
36-47	4	-18
48-59	5	-15
60-71	6	-12
72-83	7	-9
84-100	8	-6